

Release Notes

Firmware weCat3D



EN



1 **Compatibility**

The firmware version number consists of three digits (e.g. Firmware weCat3D 1.0.0).

- Major release: The first digit is changed (no compatability).
- Feature release: The second digit is changed.
- Bugfix release: The third digit is changed.

2 Change Index Firmware weCat3D

Version	Release Date
1.3.6	24.02.2026
• UserString Related Updates: Default UserString has been set to “2D/3D Profile Sensor • HDR Bugfix • Minor improvements	

Version	Release Date
1.3.5	26.01.2026
• Bugfixes • Minor improvements	

Version	Release Date
1.3.4	10.12.2025
• Bugfixes • Minor improvements	

Version	Release Date
1.3.3	03.04.2025
• Bugfix for small container size and small bandwidth • Minor improvements	

Version	Release Date
1.3.2	24.02.2025
• AutoExposureMode stabilization • Added maximum frame rate in xml • Bugfixes • Minor improvements	

Version	Release Date
1.3.1	20.11.2024
• Bugfixes • Minor improvements	

Version	Release Date
1.3.0	06.11.2024
- New commands: - SetContainerContent: Option to reduce the amount of transmitted sensor data - SetSignalContentSwap: Option to switch the order of the transmitted data <u>Example:</u> SetSignalContentSwap=0: standard SetSignalContentSwap=1: swap intern from hi/lo to lo/hi - New commands for MLWL - SetEthernetSpeedUp: Option to enable the MLWL to be operated with a measurement rate of up to 6kHz - Minor improvements	

Version	Release Date
1.2.7	11.09.2023
- Support of special devices “SetCameraMode” (deprecated) is replaced by “SetOperatingMode” - Minor improvements	